

HH	HH	PPPPPPPP	44	TTTTTTTTTT
HH	HH	PP	PP 44	TT
HH	HH	PP	PP 44 44	TT
HHHHHHHHHH	PPPPPPPP	4444444444		TT
HH	HH	PP	44	TT
HH	HH	PP	44	TT
HH	HH	PP	44	TT

HISOFT PASCAL 4 TM V1.6

C O N T E N T S

0 PRELIMINARIES

- 0.0 Getting Started
- 0.1 Scope of this Manual
- 0.2 Compiling and Running
- 0.3 Strong TYPEing

1 SYNTAX and SEMANTICS

- 1.1 IDENTIFIER
- 1.2 UNSIGNED INTEGER
- 1.3 UNSIGNED NUMBER
- 1.4 UNSIGNED CONSTANT
- 1.5 CONSTANT
- 1.6 SIMPLE TYPE
- 1.7 TYPE
- 1.7.1 ARRAYS and SETs
- 1.7.2 POINTERS
- 1.7.4 RECORDs
- 1.8 FIELD LIST
- 1.9 VARIABLE
- 1.10 FACTOR
- 1.11 TERM
- 1.12 SIMPLE EXPRESSION
- 1.13 EXPRESSION
- 1.14 PARAMETER LIST
- 1.15 STATEMENT
- 1.16 BLOCK
- 1.17 PROGRAM

2.1	CONSTANTS
2.2	TYPES
2.3	PROCEDURES and FUNCTIONS
2.3.1	Input and Output Procedures
2.3.1.1	WRITE
2.3.1.2	WRITELN
2.3.1.3	PAGE
2.3.1.4	READ
2.3.1.5	READLN
2.3.2	Input Functions
2.3.2.1	EOLN
2.3.2.2	INCH
2.3.3	Transfer Functions
2.3.3.1	TRUNC (X)
2.3.3.2	ROUND (X)
2.3.3.3	ENTIER (X)
2.3.3.4	ORD (X)
2.3.3.5	CHR (X)
2.3.4	Arithmetic Functions
2.3.4.1	ABS (X)
2.3.4.2	SQR (X)
2.3.4.3	SQRT (X)
2.3.4.4	FRAC (X)
2.3.4.5	SIN (X)
2.3.4.6	COS (X)
2.3.4.7	TAN (X)
2.3.4.8	ARCTAN (X)
2.3.4.9	EXP (X)
2.3.4.10	LN (X)
2.3.5	Further Predefined Procedures
2.3.5.1	NEW (p)
2.3.5.2	MARK (v1)
2.3.5.3	RELEASE (v1)
2.3.5.4	INLINE (C1, C2, ...)
2.3.5.5	USER (V)
2.3.5.6	HALT
2.3.5.7	POKE (X, V)
2.3.5.8	TOUT (NAME, START, SIZE)
2.3.5.9	TIN (NAME, START)
2.3.5.10	OUT (P, C)
2.3.6	Further Predefined Functions
2.3.6.1	RANDOM
2.3.6.2	SUCC (X)
2.3.6.3	PRED (X)
2.3.6.4	ODD (X)
2.3.6.5	ADDR (V)
2.3.6.6	PEEK (X, T)
2.3.6.7	SIZE (V)
2.3.6.8	INP (P)

3.1	Comments
3.2	Compiler options

4.1	Introduction to the Editor
4.2	The Editor Commands
4.2.1	Text Insertion
4.2.2	Text Listing
4.2.3	Text Editing
4.2.4	Tape Commands
4.2.5	Compiling and Running from the Editor
4.2.6	Other Commands
4.3	An Example of the Use of the Editor

Appendix 1 ERRORS

A.1.1	Error numbers generated by the compiler
A.1.2	Runtime Error Messages

Appendix 2 RESERVED WORDS and PREDEFINED IDENTIFIERS

A.2.1	Reserved Words
A.2.2	Special Symbols
A.2.3	Predefined Identifiers

Appendix 3 DATA REPRESENTATION and STORAGE

A.3.1	Data Representation
A.3.1.1	Integers
A.3.1.2	Character, Booleans and other Scalars
A.3.1.3	Reals
A.3.1.4	Records and Arrays
A.3.1.5	Sets
A.3.1.6	Pointers
A.3.2	Variable storage at Runtime

Appendix 4 ZX Spectrum SOUND, SOME EXAMPLE HP4T PROGRAMS

0.0 Getting Started

Hisoft Pascal 4T (HP4T) is a fast, easy-to-use and powerful version of the Pascal language as specified in the Pascal User Manual and Report (Jensen/Wirth Second Edition).

Omissions from the specification are as follows:

FILES are not implemented although variables may be stored on tape.

A RECORD type may not have a VARIANT part.

PROCEDURES and FUNCTIONS are not valid as parameters.

Many extra functions and procedures are included to reflect the changing environment in which compilers are used; among these are POKE, PEEK, TIN, TOUT and ADDR.

The compiler occupies approximately 12K of storage while the runtimes take up roughly 4K. Both are supplied on cassette tape in the tape format used by the runtimes. All interfacing between HP4T and the host machine takes place through vectors conveniently placed at the start of the runtimes - this makes it easy for the user to write his own customised I/O routines if necessary.

WRITE(CHR(16)) directs output to the printer (if available) or if output was going to the printer then it returns to the screen.

A simple loader is also supplied in the package so that the user can load, from tape, data which has been recorded in HP4T format.

When the compiler has been successfully loaded it will execute automatically and produce the message:

Top of RAM?

You should respond to this by either entering a positive decimal number up to 65536 (followed by ENTER) or by hitting ENTER.

If you enter a number then this is taken to represent the highest RAM location + 1 otherwise the first non-RAM location is automatically computed. The compiler's stack is set to this value and thus you can reserve high memory locations (perhaps for extensions to the compiler) by deliberately giving a value less than the true top of RAM. In the ZX Spectrum version the 'true' top of RAM is taken to be start of the user-defined graphics area (UDG in the Sinclair manual).

You will then be prompted with:

Top of RAM for 'T'

Here you can enter a decimal number or default to the 'Top of RAM' value previously specified. What you enter will be taken as the stack when the resultant object code is executed after using the editor 'T' command (See Section 4 for details). You will need to define a runtime stack different from the top of RAM if, for example, you have written extensions to the runtimes and wish to place them safely in high memory locations.

Finally you will be asked:

Table size?

What you enter here specifies the amount of memory to be allocated to the compiler's symbol table. Again, either enter a positive decimal number followed by ENTER or simply ENTER by itself in which case a default value of (available RAM divided by 16) will be taken as the symbol table size. In nearly all cases the default value provides more than enough space for symbols. The symbol table may not extend above machine address #8000*(32768 decimal). If you specify so large a value that this happens then you will be prompted again for 'Top of RAM' etc.

You may, optionally, include an 'E' before the number after this prompt - if you do so then the internal line editor will not be retained for use by the compiler. So do this if you wish to use your own editor with the compiler.

At this point the compiler and integral editor (if retained) will be relocated at the end of the symbol table and execution transferred to the supported editor.

0.1 Scope of this manual.

Section 1 gives the syntax and the semantics expected by the compiler.

Section 2 details the various predefined identifiers that are available within Hisoft Pascal 4, from CONSTANTS to FUNCTIONS.

Section 3 contains information on the various compiler options available and also on the format of comments.

Section 4 shows how to use the line editor which is an integral part of HP4T.

Appendix 1 details the error messages generated both by the compiler and the runtimes.

Appendix 2 lists the predefined identifiers and reserved words.

Appendix 3 gives details on the internal representation of data within Hisoft Pascal 4 - useful for programmers who wish to get their hands dirty.

Appendix 4 gives some example Pascal programs.

0.2 Compiling and Running.

For details of how to create, amend, compile and run an HP4T program using the integral line editor see Section 4 of this manual. For information on what to do if you are using your own editor see the HP4T Alteration Guide.

Once it has been invoked the compiler generates a listing of the form:

```
xxxx nnnn text of source line
```

where:

```
xxxx is the address where the code generated by this
line begins.
nnnn is the line number with leading zeroes suppressed.
```

If a line contains more than 80 characters then the compiler inserts new-line characters so that the length of a line is never more than 80 characters.

The listing may be directed to a printer, if required, by the use of option 'P' if supported (see Section 3).

You may pause the listing at any stage by pressing CS; subsequently use EDIT to return to the editor or any key to restart the listing.

If an error is detected during the compilation then the message '*ERROR*' will be displayed followed by an up-arrow ('^') which points after the symbol which generated the error, and an error number (see Appendix 1). The listing will pause; hit 'E' to return to EDITOR to edit the line displayed, 'P' to return to the editor and edit the previous line (if it exists) or any other key to continue the compilation.

If the program terminates incorrectly (e.g. without 'END.') then the message 'No more text' will be displayed and control returned to the editor.

If the compiler runs out of table space then the message 'No Table Space' will be displayed and control returned to the editor. Normally the programmer will then save the program on tape, re-load the compiler and specify a larger 'Table size' (see Section 0.0).

If the compilation terminates correctly but contained errors then the number of errors detected will be displayed and the object code deleted. If the compilation is successful then the message 'Run?' will be displayed; if you desire an immediate run of the program then respond with 'Y', otherwise control will be returned to the editor.

During a run of the object code various runtime error messages may be generated (see Appendix 1). You may suspend a run by using CS; subsequently use EDIT to abort the run or any other key to resume the run.

0.3 Strong TYPEing.

Different languages have different ways of ensuring that the user does not use an element of data in a manner which is inconsistent with its definition.

At the one end of the scale there is machine code where no checks whatever are made on the TYPE of variable being referenced. Next we have a language like the Byte 'Tiny Pascal' in which character, integer and Boolean data may be freely mixed without generating errors. Further up the scale comes BASIC which distinguishes between numbers and strings and, sometimes, between integers and reals (perhaps using the '%' sign to denote integers). Then comes Pascal which goes as far as allowing distinct user-enumerated types. At the top of the scale (at present) is a language like ADA in which one can define different, incompatible numeric types.

There are basically two approaches used by Pascal implementations to strength of typing; structural equivalence or name equivalence. Hisoft Pascal 4 uses name equivalence for RECORDs and ARRAYs. The consequences of this are clarified in Section 1 - let suffice to give an example here; say two variables are defined as follows:

```
VAR A:ARRAY['A'..'C']OF INTEGER;  
    B:ARRAY['A'..'C']OF INTEGER;
```

then one might be tempted to think that one could write A:=B; but this would generate an error (*ERROR* 10) under Hisoft Pascal 4 since two separate 'TYPE records' have been created by the above definitions. In other words, the user has not taken the decision that A and B should represent the same type of data. She/He could do this by:


```
VAR A,B:ARRAY['A'..'C'] OF INTEGER;
```

and now the user can freely assign A to B and vice versa since only one 'TYPE record' has been created.

Although on the surface this name equivalence approach may seem a little complicated, in general it leads to fewer programming errors since it requires more initial thought from the programmer.

This section details the syntax and the semantics of Hisoft Pascal 4 - unless otherwise stated the implementation is as specified in the Pascal User Manual and Report Second Edition (Jensen/Wirth).


1.1 IDENTIFIER.



Only the first 10 characters of an identifier are treated as significant.

Identifiers may contain lower or upper case letters. Lower case is not converted to upper case so that the identifiers HELLO, HELlo and hello are all different. Reserved words and predefined identifiers may only be entered in upper case.

1.2 UNSIGNED INTEGER.



1.3 UNSIGNED NUMBER.

```

----->-----
I                                     I
I                                     I
I ----->----- -> + --          I
I I                                     I
-> unsign.integ.----> . -> digit -> E -----> unsign.integ.->
I                                     I
I                                     I
I                                     I
I                                     I
I -----<-----
I I                                     I
-----> # -----> hexadecimal digit ----->-----

```

Integers have an absolute value less than or equal to 32767 in PASCAL 4. Larger whole numbers are treated as reals.

The mantissa of reals is 23 bits in length. The accuracy attained is therefore about 7 significant figures. Note that accuracy is lost if the result of a calculation is much less than the absolute values of its argument e.g. 2.00002 - 2 does not yield 0.00002. This is due to the inaccuracy involved in representing decimal fractions as binary fractions. It does not occur when integers of moderate size are represented as reals e.g. 200002 - 200000 = 2 exactly. The largest real available is 3.4E38 while the smallest is 5.9E-39.

There is no point in using more than 7 digits in the mantissa when specifying reals since extra digits are ignored except for their place value.

When accuracy is important avoid leading zeroes since these count as one of the digits. Thus 0.000123456 is represented less accurately than 1.23456E-4.

Hexadecimal numbers are available for programmers to specify memory addresses for assembly language linkage inter alia. Note that there must be at least one hexadecimal digit present after the '#', otherwise an error (*ERROR* 51) will be generated.

1.4 UNSIGNED CONSTANT.

```

-----> constant identifier -----
I                                     I
I-----> unsigned number ----->I
I                                     I
I-----> NIL ----->I
I                                     I
I -----<-----
I I                                     I
-----> ' -----> character -----> ' -----

```

Note that strings may not contain more than 255 characters. String types are ARRAY[1..N] OF CHAR where N is an integer between 1 and 255 inclusive. Literal strings should not contain end-of-line characters (CHR(13)) - if they do then an '*ERROR* 68' is generated.

The characters available are the full expanded set of ASCII values with 256 elements. To maintain compatibility with Standard Pascal the null character is not represented as ""; instead CHR(0) should be used.

1.5 CONSTANT.

```

-----> constant identifier ----->
I      +      I      I
->----->
I I      I I      I I I
I --> - --- ----> unsigned number ----- I I
I
I
I
I
I
I-----> ' -----> character -----> ' -----> I
I
I
-----> CHR -----> ( -----> constant -----> ) ----->

```

The non-standard CHR construct is provided here so that constants may be used for control characters. In this case the constant in parentheses must be of type integer.

E.g. CONST bs=CHR(10);
 cr=CHR(13);

1.6 SIMPLE TYPE.

```

-----> type identifier ----->
I
I
I-----> ( -----> identifier -----> ) --->I
I      I      I
I -----> , ----->
I
I
-----> constant -----> .. -----> constant ----->

```

Scalar enumerated types (identifier, identifier,) may not have more than 256 elements.

1.7 TYPE.

```

-----> simple type ----->
I
I
I-----> ^ -----> type identifier ----->I
v      I
I      I
I<-- PACKED <--
I
I
I--> ARRAY -> [ --> simple type --> ] -> OF -> type ->I
I      I      I
I ----- , <-----
I
I
I-----> SET -----> OF -----> simple type ----->I
I
I
-----> RECORD -----> field list -----> END ----->

```

The reserved word PACKED is accepted but ignored since packing already takes place for arrays of characters etc. The only case in which the packing of arrays would be advantageous is with an array of Booleans - but this is more naturally expressed as a set when packing is required.

1.7.1 ARRAYS and SETs.

The base type of a set may have up to 256 elements. This enables SETs of CHAR to be declared together with SETs of any user enumerated type. Note, however, that only subranges of integers can be used as base types. All subsets of integers are treated as sets of 0..255.

Full arrays of arrays, arrays of sets, records of sets etc. are supported.

Two ARRAY types are only treated as equivalent if their definition stems from the same use of the reserved word ARRAY. Thus the following types are not equivalent:

```
TYPE
    tablea = ARRAY[1..100] OF INTEGER;
    tableb = ARRAY[1..100] OF INTEGER;
```

So a variable of type tablea may not be assigned to a variable of type tableb. This enables mistakes to be detected such as assigning two tables representing different data. The above restriction does not hold for the special case of arrays of a string type, since arrays of this type are always used to represent similar data.

1.7.2 Pointers.

Hisoft Pascal 4 allows the creation of dynamic variables through the use of the Standard Procedure NEW (see Section 2). A dynamic variable, unlike a static variable which has memory space allocated for it throughout the block in which it is declared, cannot be referenced directly through an identifier since it does not have an identifier; instead a pointer variable is used. This pointer variable, which is a static variable, contains the address of the dynamic variable and the dynamic variable itself is accessed by including a '^' after the pointer variable. Examples of the use of pointer types can be studied in Appendix 4.

There are some restrictions on the use of pointers within Hisoft Pascal 4. These are as follows: Pointers to types that have not been declared are not allowed. This does not prevent the construction of linked list structures since type definitions may contain pointers to themselves e.g.

```
TYPE
    item = RECORD
        value : INTEGER ;
        next : ^item
    END;
    link = ^item;
```

Pointers to pointers are not allowed.

Pointers to the same type are regarded as equivalent e.g.

```
VAR
    first : link;
    current : ^item;
```

The variables first and current are equivalent (i.e. structural equivalence is used) and may be assigned to each other or compared.

The predefined constant NIL is supported and when this is assigned to a pointer variable then the pointer variable is deemed to contain no address.

1.7.4 RECORDS.

The implementation of RECORDS, structured variables composed of a fixed number of constituents called fields, within Hisoft Pascal 4 is as Standard Pascal except that the variant part of the field list is not supported.

Two RECORD types are only treated as equivalent if their declaration stems from the same occurrence of the reserved word RECORD see Section 1.7.1 above.

The WITH statement may be used to access the different fields within a record in a more compact form.

See Appendix 4 for an example of the use of WITH and RECORDS in general.

1.8 FIELD LIST.

```

----- ; <-----
I                                     I
I ----- , <-----                I
I I                                     I
-->-----> identifier ----> : ----> type ----->-
I                                     I
I                                     I
----->-----

```

Used in conjunction with RECORDS see Section 1.7.4 above and Appendix 4 for an example.

1.9 VARIABLE

```

--> variable identifier --><-----<-----
I                                     I                                     I
I                                     I                                     I
-->-----> field identifier -----> [ --> expression --> ] -->I
I                                     I                                     I
I                                     I ----- , <-----                I
I                                     I                                     I
I                                     I                                     I
I--> , --> field identifier -->I
I                                     I
I                                     I
I-----> ^ -----I
I
v

```

Two kinds of variables are supported within Hisoft Pascal 4; static and dynamic variables. Static variables are explicitly declared through VAR and memory is allocated for them during the entire execution of the block in which they were declared.

Dynamic variables, however, are created dynamically during program execution by the procedure NEW. They are not declared explicitly and cannot be referenced by an identifier. They are referenced indirectly by a static variable of type pointer, which contains the address of the dynamic variable. See section 1.7.2 and Section 2 for more details of the use of dynamic variables and Appendix 4 for an example.

When specifying elements of multi-dimensional arrays the programmer is not forced to use the same form of index specification in the reference as was used in the declaration.

1.10 FACTOR.

```

-----> unsigned constant ----->-
I
I
I-----> variable ----->I
I
I
I--> function identifier ---> ( --> expression --> ) --->I
I          I          I          I          I
I          I          -----> , -----
I          I
I          ----->I
I
I-----> ( -----> expression -----> ) ----->I
I
I
I--> NOT -----> factor ----->I
I
I
I          ----->-----
I          I          I
----> [ ----> expression ----> .. --> expression ----> ] ---
I          I          I I
I          ----->----- I
I          I
-----> , -----

```

See EXPRESSION in Section 1.13 and FUNCTION in Section 3 for more details.

1.11 TERM.

```

----> factor ----->-
I          I          I          I          I          I
I
I          +          /          DIV          MOD          AND
I
I          I          I          I          I          I
-- factor <-----

```

he lowerbound of a set is always zero and the set size is always the maximum of the base type of the set. Thus a SET OF CHAR always occupies 32 bytes (a possible 256 elements - one bit for each element). Similarly a SET OF 0..10 is equivalent to SET OF 0..255.

1.12 SIMPLE EXPRESSION.


```

-----> + -----
I          I
-----> term ----->-
I          I          I          I          I          I
----> - ----
I          I          +          -          CR
I
I          I          I          I
-- term <-----

```

The same comments made in Section 1.11 concerning sets apply to simple expressions.


1.13 EXPRESSION.



When using IN, the set attributes are the full range of the type of the simple expression with the exception of integer arguments for which the attributes are taken as if [0..255] had been encountered.

The above syntax applies when comparing strings of the same length, pointers and all scalar types. Sets may be compared using >=, <=, <> or =. Pointers may only be compared using = and <>.

1.14 PARAMETER LIST.



A type identifier must be used following the colon - otherwise *ERROR* 44 will result.

Variable parameters as well as value parameters are fully supported.

Procedures and functions are not valid as parameters.

1.15 STATEMENT.

Refer to the syntax diagram on page below.

Assignment statements:

See section 1.7 for information on which assignment statements are illegal.

CASE statements:

An entirely null case list is not allowed i.e. CASE OF END; will generate an error (*ERROR* 13).

The ELSE clause, which is an alternative to END, is executed if the selector ('expression' overleaf) is not found in one of the case lists ('constant' overleaf).

If the END terminator is used and the selector is not found then the control is passed to the statement following the END.

FOR statements:

The control variable of a FOR statement may only be an unstructured variable, not a parameter. This is half way between Jensen/Wirth and draft ISO standard definitions.

GOTO statements:

It is only possible to GOTO a label which is present in the same block as the GOTO statement and at the same level.

Labels must be declared (using the Reserved Word LABEL) in the block in which they are used; a label consists of at least one and up to four digits. When a label is used to mark a statement it must appear at the beginning of the statement and be followed by a colon - ':'.
:

STATEMENT.

```

-----
--> unsigned integer --> : ---
I
I
I
I
>-----> variable identifier ----> := ----> expression ----->>
I I I I
I --> function identifier ---
I
I ----- , < -----
I I I
I----> procedure identifier ----> ( ----> expression ----> ) -->I
I I I
I ----->I
I
I----> BEGIN -----> statement -----> END ----->I
I I I
I ----- ; <-----
I ----->I
I I
I> IF > expression > THEN > statement --> ELSE > statement >I
I I
I
I ----->-----
I I I
I> CASE > expression > OF > constant > : > statement > END >I
I I I I
I I--- , <---- I I
I I I
I ----- ; <-----I
I I
I -----
I I
I --> ELSE --> statement -->I
I
I----> WHILE ---> expression ---> DO ---> statement ----->I
I
I----> REPEAT ---> statement ---> UNTIL -----> expression --->I
I I I
I ----- ; <-----
I
I-> FOR -> variable identifier -> := -> expression -> TO -
I I I
I I I
I ----- DOWNTO <----- I I
I I I
I I<-----
I I
I --> expression --> DO --> statement -->I
I
I----> WITH ---> variable ---> DO ---> statement ----->I
I I I
I ----- , <-----
I
I----> GOTO ---> unsigned integer ----->I
I
----->-----
I
I
V

```


1.16 BLOCK.

```

>---> LABEL -----> unsigned integer -----
I          ^
I<----- ; <----- , -----
I
I
I---> CONST ---> identifier ---> = ---> constant -----
I          I
I          ^
I<----- ; <-----
I
I
I---> TYPE ----> identifier ---> = ---> type -----
I          I
I          ^
I----- ; <-----
I
I
I---> VAR -----> identifier ---> : ---> type -----
I          I          I
I          I<----- , <-----
I          I
I<----- ; <-----
I
I
I---> PROCEDURE ---> identifier ---> parameter list ----->I
I          I          I
I          -----
I          I
I          ---> ; ---> FORWARD --->I
I          I
I
I> FUNCTION > identifier > parameter list > : > type ident.->
I          I
I
I<----- ; <----- block <----- ; <-----
I
I
I---> BEGIN ---> statement ---> END ----->-
I          I          I
I----- ; <-----

```

Note that, when a file variable is declared, then it may be followed, optionally, by a constant with a value between 1 and 255 inclusive enclosed in square brackets. This constant specifies the buffer size used for this file, in 128 character units. For example if you require the file file1 to have a buffer size of 2K (2048 characters) then the declaration should look like:

```
VAR file1 : FILE OF CHAR[16];
```

or

```
CONST filesize = 16;
VAR file1 : TEXT[filesize];
```

Forward References.

As in the Pascal User Manual and Report (Section 11.C.1) procedures and functions may be referenced before they are declared through use of the Reserved Word FORWARD e.g.

```
PROCEDURE a(y:t) ; FORWARD;      (*procedure a declared to be*)
PROCEDURE b(x:t);                (*forward of this statement*)
  BEGIN
  ....
  a(p);                           (*procedure a referenced.*)
  ....
  END;
PROCEDURE a;                      (*actual declaration of procedure a.*)
  BEGIN
  ....
  b(g);
  ....
  END;
```

Note that the parameters and result type of the procedure a are declared along with FORWARD and are not repeated in the main declaration of the procedure. Remember, FORWARD is a Reserved Word.

1.17 PROGRAM.

```
--> PROGRAM --> identifier --> ; --> block --> END -->-
```

Since files are not implemented there are no formal parameters of the program.

2 PREDEFINED IDENTIFIERS.

2.1 CONSTANTS.

MAXINT The largest integer available i.e. 32767.
TRUE, FALSE The constants of type Boolean.

2.2 TYPES.

INTEGER See Section 1.3.
REAL See Section 1.3.
CHAR The full extended ASCII character set of 256
 elements.
BOOLEAN (TRUE,FALSE). This type is used in logical
 operations including the results of
 comparisons.

2.3 PROCEDURES AND FUNCTIONS.

2.3.1 Input and Output Procedures.

2.3.1.1 WRITE

The procedure WRITE is used to output data to the screen or printer. When the expression to be written is simply of type character then WRITE(e) passes the 8 bit value represented by the value of the expression e to the screen or printer as appropriate.

Note:

CHR(8) (CTRL H) gives a destructive backspace on the screen.

CHR(12) (CTRL L) clears the screen or gives a new page on the printer.

CHR(13) (CTRL M) performs a carriage return and line feed.

CHR(16) (CTRL P) will normally direct output to the printer if the screen is in use or vice versa.

Generally though:

WRITE(P1,P2,.....Pn); is equivalent to:

BEGIN WRITE(P1); WRITE(P2);; WRITE(Pn) END;

The write parameters P1,P2,.....Pn can have one of the following forms:

<e> or <e:m> or <e:m:n> or <e:m:H>

where e,m and n are expressions and H is a literal constant.

We have 5 cases to examine:

1] e is of type integer: and either <e> or <e:m> is used.

The value of the integer expression e is converted to a character string with a trailing space. The length of the string can be increased (with leading spaces) by the use of m which specifies the total number of characters to be output. If m is not sufficient for e to be written or m is not present then e is written out in full, with a trailing space, and m is ignored. Note that, if m is specified to be the length of e without the trailing space then no trailing space will be output.

2] e is of type integer and the form <e:m:H> is used.

In this case e is output in hexadecimal. If m=1 or m=2 then the value (e MOD 16^m) is output in a width of exactly m characters. If m=3 or m=4 then the full value of e is output in hexadecimal in a width of 4 characters. If m>4 then leading spaces are inserted before the full hexadecimal value of e as necessary. Leading zeroes will be inserted where applicable.

Examples:

```

WRITE(1025:m:H);
m=1      outputs: 1
m=2      outputs: 01
m=3      outputs: 0401
m=4      outputs: 0401
m=5      outputs: _0401

```

3] e is of type real. The forms <e> <e:m> or <e:m:n> may be used.

The value of e is converted to a character string representing a real number. The format of the representation is determined by n.

If n is not present then the number is output in scientific notation, with a mantissa and an exponent. If the number is negative the a minus sign is output prior to the mantissa, otherwise a space is output. The number is always output to at least one decimal place up to a maximum of 5 decimal places and the exponent is always signed (either with a plus or minus sign). This means that the minimum width of the scientific representation is 8 characters; if the field width m is less than 8 then the full width of 12 characters will always be output. If m>=8 then one or more decimal places will be output up to a maximum of 5 decimal places (m=12). For m>12 leading spaces are inserted before the number. Examples:

```

WRITE(-1.23E 10:M);
m=7      gives: -1.23000E+10
m=8      gives: -1.2E+10
m=9      gives: -1.23E+10
m=10     gives: -1.230E+10
m=11     gives: -1.2300E+10
m=12     gives: -1.23000E+10
m=13     gives: _-1.23000E+10

```

If the form <e:m:n> is used then a fixed-point representation of the number e will be written with n specifying the number of decimal places to be output. No leading spaces will be output unless the field width m is sufficiently large. If n is zero then e is output as an integer. If e is too large to be output in the specified field width then it is output in scientific format with a field width of m (see above).

Examples:

```

WRITE(1E2:6:2)      gives: 100.00
WRITE(1E2:8:2)      gives: __100.00
WRITE(23.455:6:1)   gives: __23.5
WRITE(23.455:4:2)   gives: _2.34550E+01
WRITE(23.455:4:0)   gives: __23

```

4] e is of type character or type string.

Either <e> or <e:m> may be used and the character or string of characters will be output in a minimum field width of 1 (for characters) or the length of the string (for string types). Leading spaces are inserted for m is sufficiently large.

5] e is of type Boolean.

Either <e> or <e:m> may be used and 'TRUE' or 'FALSE' will be output depending on the Boolean value of e , using a minimum field width of 4 or 5 respectively.

2.3.1.2 WRITELN

```

WRITELN output gives a newline. This is
equivalent to WRITE(CHR(13)). Note that
a linefeed is included.
WRITELN(P1,P2,.....P3); is equivalent to:
BEGIN WRITE(P1,P2,.....P3); WRITELN END;

```

2.3.1.3 PAGE

```

The procedure PAGE is equivalent to
WRITE(CHR(12)); and causes the video screen to
be cleared or the printer to advance to the
top of a new page.

```

2.3.1.4 READ

The procedure READ is used to access data from the keyboard. It does this through a buffer held within the runtimes - this buffer is initially empty (except for an end-of-line marker). We can consider that any accesses to this buffer take place through a text window over the buffer through which we can see one character at a time. If this text window is positioned over an end-of-line marker then before the read operation is terminated a new line of text will be read into the buffer from the keyboard. While reading in this line all various control codes detailed in Section 0.0 will be recognised. Now:

```
READ(V1,V2,.....Vn); is equivalent to:  
BEGIN READ(V1); READ (V2); ....; READ(Vn) END;  
where V1, V2 etc. may be of type character,  
string, integer or real.
```

The statement READ(V); has different effects depending on the type of V. There are 4 cases to consider:

1] V is of type character.

In this case READ(V) simply reads a character from the input buffer and assigns it to V. If the text window on the buffer is positioned on a line marker (a CHR(13) character) then the function EOLN will return the value TRUE and a new line of text is read in from the keyboard. When a read operation is subsequently performed then the text window will be positioned at the start of the new line.

Important note: Note that EOLN is TRUE at the start of the program. This means that if the first READ is of type character then a CHR(13) value will be returned followed by the reading in of a new line from the keyboard; a subsequent read of type character will return the first character from this new line, assuming it is not blank. See also the procedure READLN below.

2] V is of type string.

A string of characters may be read using READ and in this case a series of characters will be read until the number of characters defined by the string has been read or EOLN = TRUE. If the string is not filled by the read (i.e. if end-of line is reached before the whole string has been assigned) then the end of the string is filled with null (CHR(0)) characters - this enables the programmer to evaluate the length of the string that was read.

The note concerning in 1] above also applies here.

3] V is of type integer.

In this case a series of characters which represent an integer as defined in Section 1.3 is read. All preceding blanks and end-of line markers are skipped (this means that integers may be read immediately cf. the note in 1] above).

If the integer read has an absolute value greater than MAXINT (32767) then the runtime error 'Number too large' will be issued and execution terminated.

If the first character read, after spaces and end-of-line characters have been skipped, is

not a digit or a sign ('+' or '-') then a runtime error 'Number expected' will be reported and the program aborted.

4] V is of type real.

Here, a series of characters representing a real number according to the syntax of Section 1.3 will be read.

All leading spaces and end-of-line markers are skipped and, as for integers above, the first character afterwards must be a digit or a sign. If the number read is too large or too small (see Section 1.3) then an 'Overflow' error will be reported, if 'E' is present without a following sign or digit then 'Exponent expected' error will be generated and if a decimal point is present without a subsequent digit then a 'Number expected' error will be given.

Reals, like integers, may be read immediately; see 1] and 3] above.

2.3.1.5 READLN

```
READLN(V1,V2,.....Vn); is equivalent to:  
BEGIN READ(V1,V2,.....Vn);  
READLN END;
```

READLN simply read in a new buffer from the keyboard; while typing in the buffer you may use the various control functions detailed in Section 0.0. Thus EOLN becomes FALSE after the execution of READLN unless the next line is blank.

READLN may be used to skip the blank line which is present at the beginning of the execution of the object code i.e. it has the effect of reading in a new buffer. This will be usefull if you wish to read a component of type character at the beginning of a program but it is not necessary if you are reading an integer or a real (since end-of-line markers are skipped) or if you are reading characters from subsequent lines.

2.3.2 Input Functions.

2.3.2.1 EOLN

The function EOLN is a Boolean function which returns the value TRUE if the next char to be read would be an end-of-line character (chr(13)). Otherwise the function returns the value FALSE.

2.3.2.2 INCH

The function INCH causes the keyboard of the computer to be scanned and, if a key has been pressed, returns the character represented by the key pressed. If no key has been pressed, then CHR(0) is returned. The function therefore returns a result of type character.

2.3.3 Transfer Functions.

2.3.3.1 TRUNC(X)

The parameter X must be of type real or integer and the value returned by TRUNC is the greatest integer less than or equal to X if X is positive or the least integer greater than or equal to X if X is negative. Examples:

```
TRUNC(-1.5) returns -1
TRUNC(1.9) returns 1
```

2.3.3.2 ROUND(X)

X must be of type real or integer and the function returns 'nearest' integer to X (according to standard rounding rules).

Examples:

```
ROUND(-6.5) returns -6
ROUND(-6.51) returns -7
ROUND(11.7) returns 12
ROUND(23.5) returns 24
```

2.3.3.3 ENTIER(X)

X must be of type real or integer - ENTIER returns the greatest integer less than or equal to X, for all X. Examples:

```
ENTIER(-6.5) returns -7
ENTIER(11.7) returns 11
```

Note: ENTIER is not a Standard Pascal function but is the equivalent of BASIC's INT. It is useful when writing fast routines for many mathematical applications.

2.3.3.4 ORD(X)

X may be of any scalar type except real. The value returned is an integer representing the ordinal number of the value of X within the set defining the type of X.

If X is of type integer then ORD(X)=X; this should normally be avoided.

Examples:

```
ORD('a') returns 97
ORD('@') returns 64
```

2.3.3.5 CHR(X)

X must be of type integer. CHR returns a character value corresponding to the ASCII value of X. Examples:

```
CHR(49) returns '1'
CHR(91) returns 'I'
```

2.3.4 Arithmetic Functions.

In all the functions within this sub-section the parameter X must be of type real or integer.

2.3.4.1 ABS(X)

Returns the absolute value of X (e.g.ABS(-4.5) gives 4.5). The result is of the same type as X.

2.3.4.2 SQR(X)

Returns the value X*X i.e. the square of X. The result is of the same type as X.

2.3.4.3 SQRT(X)

Returns the square root of X - the returned value is always of type real. A 'Maths Call Error' is generated if the argument X is negative.

2.3.4.4 FRAC(X)

Returns the fractional part of X:
 $FRAC(X) = X - ENTIER(X)$.
As with ENTIER this function is useful for writing many fast mathematical routines.
Examples:
FRAC(1.5) returns 0.5
FRAC(-12.56) returns 0.44

2.3.4.5 SIN(X)

Returns the sine of X where X is in radians. The result is always of type real.

2.3.4.6 COS(X)

Returns the cosine of X where X is in radians. The result is of type real.

2.3.4.7 TAN(X)

Returns the tangent of X where X is in radians. The result is always of type real.

2.3.4.8 ARCTAN(X)

Returns the angle, in radians, whose tangent is equal to the number X. The result is of type real.

2.3.4.9 EXP(X)

Returns the value e^X where $e=2.71828$. The result is always of type real.

2.3.4.10 LN(X)

Returns the natural logarithm (i.e. to the base e) of X. The result is of type real. If $X \leq 0$ then a 'Maths Call Error' will be generated.

2.3.5 Further Predefined Procedures.

2.3.5.1 NEW(p)

The procedure NEW(p) allocates space for a dynamic variable. The variable p is a pointer variable and after NEW(p) has been executed p contains the address of the newly allocated dynamic variable. The type of the dynamic variable is the same as the type of the pointer variable p and this can be of any

type.

To access the dynamic variable p^{\wedge} is used - see Appendix 4 for an example of the use of pointers to reference dynamic variables. To re-allocate space used for dynamic variables use the procedures MARK and RELEASE (see below).

2.3.5.2 MARK(v1)

This procedure saves the state of the dynamic variable heap to be saved in the pointer variable v1. The state of the heap may be restored to that when the procedure MARK was executed by using the procedure RELEASE (see below).

The type of variable to which v1 points is irrelevant, since v1 should only be used with MARK and RELEASE never NEW.

For an example program using MARK and RELEASE see Appendix 4.

2.3.5.3 RELEASE(v1)

This procedure frees space on the heap for use of dynamic variables. The state of the heap is restored to its state when MARK(v1) was executed - thus effectively destroying all dynamic variables created since the execution of the MARK procedure. As such it should be used with great care.

See above and Appendix 4 for more details.

2.3.5.4 INLINE(C1,C2,C3,.....)

This procedure allows Z80 machine code to be inserted within the Pascal program; the values (C1 MOD 256, C2 MOD 256, C3 MOD 256,) are inserted in the object program at the current location counter address held by the compiler. C1, C2, C3 etc. are integer constants of which there can be any number. Refer to Appendix 4 for an example of the use of INLINE.

2.3.5.5 USER(V)

USER is a procedure with one integer argument V. The procedure causes a call to be made to the memory address given by V. Since Hisoft Pascal 4 holds integers in two's complement form (see Appendix 3) then in order to refer to addresses greater than #7FFF (32767) negative values of V must be used. For example #C000 is -16384 and so USER(-16384); would invoke as a call to the memory address #C000. However, when using a constant to refer to a memory address, it is more convenient to use hexadecimal.

The routine called should finish with a Z80 RET instruction (#C9) and must preserve the IX register.

2.3.5.6 HALT

This procedure causes program execution to stop with the message 'Halt at the PC=XXXX' where XXXX is the hexadecimal memory address of the location where the HALT was issued. Together with a compilation listing, HALT may be used to determine which of two or more paths through a program are made. This will normally be used during de-bugging.

2.3.5.7 POKE(X,V)

POKE stores the expression V in the computer's memory address X. X is of type integer and V can be of any type except SET. See Section 2.3.5.5 above for a discussion of the use of integers to represent memory addresses.

Examples:

```
POKE(#6000,'A') places #41 at location #6000.
POKE(-16384,3.6E3) places 00 0E 80 70 (in
hexadecimal) at location #C000.
```

2.3.5.8 TOUT (NAME,START,SIZE)

TOUT is the procedure which is used to save variables on tape. The first parameter is of type ARRAY[1..8] OF CHAR and is the name of the file to be saved. SIZE bytes of memory are dumped starting at the address START. Both these parameters are of type INTEGER. E.g. to save the variable V to tape under the name 'VAR ' use:

```
TOUT('VAR ',ADDR(V),SIZE(V))
```

The use of actual memory addresses gives the user far more flexibility than just the ability to save arrays. For example if a system has a memory mapped screen, entire screenfuls may be saved directly. See Appendix 4 for an example of the use of TOUT.

2.3.5.9 TIN(NAME,START)

This procedure is used to load, from tape, variable etc. that have been saved using TOUT. NAME is of type ARRAY[1..8] of CHAR and START is of type INTEGER. The tape is searched for a file called NAME which is then loaded at memory address START. The number of bytes to load is taken from the tape (saved on the tape by TOUT).

E.g. to load the variable saved in the example in Section 2.3.5.8 above use:

```
TIN('VAR '),ADDR(V)
```

Because source files are recorded by the editor using the same format as that used by TIN and TOUT, TIN may be used to load text files into ARRAYS of CHAR for processing (see the HP4T Alteration Guide).

See Appendix 4 for an example of the use of TIN.

2.3.5.10 OUT(P,C)

This procedure is used to directly access the Z80's output ports without using the procedure INLINE. The value of the integer parameter P is loaded in to the BC register, then the character parameter C is loaded in to the A register and the assembly instruction

```
OUT (C),A is executed.
```

E.g. OUT(1,'A') outputs the character 'A' to the Z80 port 1.

2.3.6 Further Predefined Functions.

2.3.6.1 RANDOM

This returns a pseudo-random number between 0 and 255 inclusive. Although this routine is very fast it gives poor results when used repeatedly within loops that do not contain I/O operations.

If the user requires better results than this function yields then he/she should write a routine (either in Pascal or machine code) tailored to the particular application.

2.3.6.2 SUCC(X)

X may be of any scalar type except real and SUCC(X) returns the successor of X. Examples:

```
SUCC('A') returns 'B'
SUCC('5') returns '6'
```

2.3.6.3 PRED(X)

X may be of any scalar type except real; the result of the function is the predecessor of X. Examples:

```
PRED('j') returns 'i'
PRED(TRUE) returns FALSE
```

2.3.6.4 ODD(X)

X must be of type integer, ODD returns a Boolean result which is TRUE if X is odd and FALSE if X is even.

2.3.6.5 ADDR(V)

This function takes a variable identifier of any type as a parameter and returns an integer result which is the memory address of the variable identifier V. For information on how variables are held, at runtime, within Hisoft Pascal 4 see Appendix 3. For an example of the use of ADDR see Appendix 4.

2.3.6.6 PEEK(X,T)

The first parameter of this function is of type integer and is used to specify a memory address (see Section 2.3.5.5). The second argument is a type : this is the result type of the function.

PEEK is used to retrieve data from the memory of the computer and the result may be of any type.

In all PEEK and POKE (the opposite of PEEK) operations data is moved in Hisoft Pascal 4's own internal representation detailed in Appendix 3. For example: if the memory from #5000 onwards contains the values:

```
50 61 73 63 61 6C (in hexadecimal) then:
WRITE(PEEK(#5000,ARRAY[1..6] OF CHAR)) gives
'Pascal'
```

```
WRITE(PEEK(#5000,CHAR)) gives 'P'
```

```
WRITE(PEEK(#5000,INTEGER)) gives 24912
```

```
WRITE(PEEK(#5000,REAL)) gives 2.46227E+29
```

see Appendix 3 for more details on the representation of types within Hisoft Pascal 4.

2.3.6.7 SIZE(V)

The parameter of this function is a variable. The integer result is the amount of storage taken up by that variable, in bytes.

2.3.6.8 INP(P)

INP is used to access the Z80's ports directly without using the procedure INLINE. The value of the integer parameter P is loaded into the BC register and the character result of the function is obtained by executing the assembly language instruction IN A, (C).

3 COMMENTS AND COMPILER OPTIONS.

3.1 Comments.

A comment may occur between any two reserved words, numbers, identifiers or special symbols - see Appendix 2. A comment starts with a '{' character or the '(' character pair. Unless the next character is a '\$' all characters are ignored until the next '}' character or ')' character pair. If a '\$' was found then the compiler looks for a series of compiler options (see below) after which characters are skipped until a '}' or '*' is found.

3.2 Compiler Options.

The syntax for specifying compiler options is:

```
          ---> + ---
          I      I
---> $ -----> letter ----->
      I          I      I      I
      I          ---> - ---      I
      I          , <-----
          -----
```

The following options are available:

Option L:

Controls the listing of the program text and object code address by the compiler.
If L+ then a full listing is given.
If L- then lines are only listed when an error is detected.
DEFAULT: L+

Option O:

Controls whether certain overflow checks are made. Integer multiply and divide and all real arithmetic operations are always checked for overflow.
If O+ then checks are made on integer addition and subtraction
If O- then the above checks are not made.
DEFAULT: O+

Option C:

Controls whether or not keyboard checks are made during object code program execution.
If C+ then if EDIT is pressed then execution will return to with a HALT message - see Section 2.3.5.6.
This check is made at the beginning of all loops, procedures and functions. Thus the user may use this facility to detect which loop etc. is not terminating correctly during the debugging process. It should certainly be disabled if you wish the object program to run quickly.
If C- then the above check is not made.
DEFAULT: C+

Option S:

Controls whether or not stack checks are made.
If S+ then, at the beginning of each procedure and function call, a check is made to see if the stack will probably overflow in this block. If the runtime stack overflows the dynamic variable heap or the program then the message 'Out of RAM at PC=XXXX' is displayed and execution aborted. Naturally this is not foolproof; if a procedure has a large amount of stack usage within itself then the program may 'crash'. Alternatively, if a function contains very little stack usage while utilizing recursion then it is possible for the function to be halted unnecessarily.
If S- then no stack checks are performed.
DEFAULT: S+

Option A:

Controls whether checks are made to ensure that array indices are within the bounds specified in the array's declaration. If A+ and an array index is too high or too low then the message 'Index too high' or 'Index too low' will be displayed and the program execution halted.
If A- then no such checks are made.
DEFAULT: A+

Option I:

When using 16 bit 2's complement integer arithmetic, overflow occurs when performing a >, <, >=, or <= operation if the arguments differ by more than MAXINT (32767). If this occurs then the result of the comparison will be incorrect. This will not normally present any difficulties; however, should the user wish to compare such numbers, the use of I+ ensures that the results of the comparison will be correct. The equivalent situation may arise with real arithmetic in which case an overflow error will be issued if the arguments differ by more than approximately 3.4E38 ; this cannot be avoided.
If I- then no check for the result of the above comparisons is made.
DEFAULT: I-

Option P:

If the P option is used the device to which the compilation listing is sent is changed i.e. if the video screen was being used the printer is used and vice versa. Note that this option is not followed by a '+' or '-'.
DEFAULT: The video screen is used.

Option F:

This option letter must be followed by a space and then an eight character filename. If the filename has less than eight characters it should be padded with spaces.

The presence of this option causes inclusion of Pascal source text from the specified file from the end of the current line - useful if the programmer wishes to build up a 'library' of much-used procedures and functions on tape and then include them in particular programs.

The program should be saved using the built-in editor's 'P' command. On most systems the list option L- should be used - otherwise the compiler will not compile fast enough.

Example: (*\$L-,F MATRIX include the text from a tape file MATRIX*);

When writing very large programs there may not be enough room in the computer's memory for the source and object code to be present at the same time. It is however possible to compile such programs by saving them to tape and using the 'F' option - then only 128 bytes of the source are in RAM at any one time, leaving much more room for the object code. This option may not be nested and is not implemented in the ZX Spectrum version. (*In the HP4S ZX Spectrum version this option is implemented. The Pascal source text, which is to be included, should be saved using the built-in editor's command, instead of 'P'.*)

The compiler options may be used selectively. Thus debugged sections of code may be speeded up and compacted by turning the relevant checks off whilst retaining checks on untested pieces of code.

4.1 Introduction to the Editor.

The ZX SPECTRUM keyword entry scheme is not supported (we see this as a positive advantage), instead all text must be inserted using the normal alphanumeric keys. Using SYMBOL SHIFT and key (except I) will always reach the ASCII symbol associated with that key and not the keyword e.g. SYMBOL SHIFT T gives '>' and SYMBOL SHIFT G gives '}'. You must not use the single symbols <=, <> and >=; instead these should be entered as a combination of the symbols <, > and =. The editor comes up in upper case mode, this may be toggled in the normal way using CAPS SHIFT and 2.

The editor supplied with all versions of Hisoft Pascal 4T is a simple, line-based editor designed to work with all Z80 operating systems while maintaining ease of use and the ability to edit programs quickly and efficiently. Text is held in memory in a compacted form; the number of leading spaces in a line is held as one character at the beginning of the line and all HP4T Reserved Words are tokenised into one character. This leads to a typical reduction in text size of 25%.

The editor is entered automatically when HP4T is loaded from tape and displays the message:

Copyright Hisoft 1982

All rights reserved

followed by the editor prompt '>'.

In response to the prompt you may enter a command line of the following format:

C N1, N2, S1, S2

followed by a ENTER where:

C is the command to be executed (see Section 4.2 below).

N1 is a number in the range 1 - 32767 inclusive.

N2 is a number in the range 1 - 32767 inclusive.

S1 is a string of characters with a maximum length of 20.

S2 is a string of characters with a maximum length of 20.

The comma is used to separate the various arguments (although this can be changed - see the 'S' command) and spaces are ignored, except within the strings. None of the arguments are mandatory although some of the commands (e.g. the 'D' delete command) will not proceed without N1 and N2 being specified. The editor remembers the previous numbers and strings that you entered and uses these former values, where applicable, if you do not specify a particular argument within the command line. The values of N1 and N2 are initially set to 10 and the strings are initially empty. If you enter an illegal command line such as F-1,100,HELLO then the line will be ignored and the message 'Pardon?' displayed - you should then retype the line correctly e.g. F1,100,HELLO. This error message will also be displayed if the length of S2 exceeds 20; if the length of S1 is greater than 20 then any excess characters are ignored. Commands may be entered in upper or lower case.

While entering a command line, all the relevant control functions described in Section 0.0 may be used e.g. CS+5 to delete to the beginning of the line.

Command: L <n,m>

This lists the current text to the display device from line number n to line number m inclusive. The default value for n is always 1 and the default value for m is always 32767 i.e. default values are not taken from previously entered arguments. To list the entire textfile simply use 'L' without any arguments. Screen lines are formatted with a left hand margin so that the line number is clearly displayed. The number of screen lines listed on the display device may be controlled through use of the 'K' command - after listing a certain number of lines the list will pause (if not yet at line number m), hit control function EDIT to return to the main editor loop or any other key to continue the listing.

Command: K n

'K' sets the number of screen lines to be listed to the display device before the display is paused as described in 'L' above. The value (n MOD 256) is computed and stored. For example use K5 if you wish a subsequent 'L'ist to produce five screen lines at a time.

4.2.3 Text Editing.

Once some text has been created there will inevitably be a need to edit some lines. Various commands are provided to enable lines to be amended, deleted, moved and renumbered:

Command: D <n,m>

All lines from n to m inclusive are deleted from the textfile. If m<n or less than two arguments are specified then no action will be taken; this is to help prevent careless mistakes. A single line may be deleted by making m=n ; this can also be accomplished by simply typing the line number followed by ENTER.

Command: M n,m

This causes the text at line n to be entered at line m deleting any text that already exists there. Note that line n is left alone. So this command allows you to 'M'ove a line of text to another position within the textfile. If line number n does not exist then no action is taken.

Command: N <n,m>

Use of the 'N' command causes the textfile to be renumbered with a first line number of n and in line number steps of m. Both n and m must be present and if the renumbering would cause any line number to exceed 32767 then the original numbering is retained.

Command: F n,m,f,s

The text existing within the line range n<x<m is searched for an occurrence of the string f - the 'find' string. If such an occurrence is found then the relevant text line is displayed and the Edit mode is entered - see below. You may then use commands within the Edit mode to search for subsequent occurrences of the string f within the defined line range or to substitute the string s (the 'substitute' string) for the current occurrence of f and then search for the next occurrence of f; see below for more details.

Note that the line range and the two strings may have been set up previously by any other command so that it may only be necessary to enter 'F' to initiate the search - see the example in Section 4.3 for clarification.

Command: V

The 'V' command takes no arguments and simply displays the current default values of the line range, the Find string and the Substitute string. The current default line range is shown first followed by the two strings (which may be empty) on separate lines. It should be remembered that certain editor commands (like 'D' and 'N') do not use these default values but must have values specified on the command line.

Command: E n

Edit the line with line number n. If n does not exist then no action is taken; otherwise the line is copied into a buffer and displayed on the screen (with the line number), the line number is displayed again underneath the line and the Edit mode is entered. All subsequent editing takes place within the buffer and not in the text itself; thus the original line can be recovered at any time. In this mode a pointer is imagined moving through the line (starting at the first character) and various sub-commands are supported which allow you to edit the line. The sub-commands are:

' ' (space) - increment the text pointer by one i.e. point to the next character in the line. You cannot step beyond the end of the line.

DELETE (or BACKSPACE) - decrement the text pointer by one to point at the previous character in the line. You cannot step backwards beyond the first character in the line.

CS+8 (control function) - step the text pointer forwards to the next tab position but not beyond the end of the line.

ENTER - end the edit of this line keeping all the changes made.

Q - quit the edit of this line i.e. leave the edit ignoring all the changes made and leaving the line as it was before the edit was initiated.

R - reload the edit buffer from the text i.e. forget all changes made on this line and restore the line as it was originally.

L - list the rest of the line being edited i.e. the remainder of the line beyond the current pointer position. You remain in the Edit mode with the pointer re-positioned at the start of the line.

K - kill (delete) the character at the current pointer position.

Z - delete all characters from (and including) the current pointer position to the end of the line.

F - find the next occurrence of the 'find' string previously defined within a command line (see the 'F' command above). This sub-command will automatically exit the edit on the current line (keeping the changes) if it does not find another occurrence of the 'find' string in the current line. If an occurrence of the 'find' string is detected in a subsequent line (within the previously specified line range) then the Edit mode will be entered for the line in which the string is found. Note that the text pointer is always positioned at the start of the line after a successful search.

S - substitute the previously defined 'substitute' string for the currently found occurrence of the 'find' string and then perform the sub-command 'F' i.e. search for the next occurrence of the 'find' string. This, together with the above 'F' sub-command, is used to step through the textfile optionally replacing occurrences of the 'find' string with the 'substitute' string - see Section 4.3 for an example.

I - insert characters at the current pointer position. You will remain in this sub-mode until you press ENTER - this will return you to the main Edit mode with the pointer positioned after the last character that you inserted. Using DELETE (or BACKSPACE) within this sub-mode will cause the character to the left of the pointer to be deleted from the buffer while the use of CS+8 (control function) will advance the pointer to the next tab position, inserting spaces.

X - this advances the pointer to the end of the line and automatically enters the insert sub-mode detailed above.

C - change sub-mode. This allows you to overwrite the character at the current pointer position and then advances the pointer by one. You remain in the change sub-mode until you press ENTER whence you are taken back to the Edit mode with the pointer positioned after the last character you changed. DELETE (or BACKSPACE) within this sub-mode simply decrements the pointer by one i.e. moves it left while CS+8 has no effect.

4.2.4 Tape Commands.

Text may be saved to tape or loaded from tape using the commands 'P' and 'G':

Command: P n,m,s

The line range defined by n<x<m is saved to tape in HP4T format under the filename specified by the string s. Remember that these arguments may have been set by a previous command. Before entering this command make sure that your tape recorder is switched on and in RECORD mode. While the text is being saved the message 'Busy..' is displayed.

Command: G,,s

The tape is searched for a file in HP4T tape format and with a filename of s. While the search is taking place the message 'Busy..' will be displayed. If a valid HP4T tape file is found but has the wrong filename then the message 'Found' followed by the filename that was found on the tape is displayed and the search continued. Once the correct filename is found then 'Found' will appear on the list device and the file will be loaded into memory. If an error is detected during the load then 'Checksum error' is shown and the load aborted. If this happens you must rewind the tape, press PLAY and type 'G' again.

If the string s is empty then the first HP4T file on the tape will be loaded, regardless of its filename.

While searching of the tape is going on you may abort the load by holding EDIT down; this will interrupt the load and return to the main editor loop.

Note that if any textfile is already present then the textfile that is loaded from tape will be appended to the existing file and the whole file will be renumbered starting with line 1 in steps of 1.

Command: W n,m,s

The line range n<x<m is saved to tape under the filename specified by the string s, in a format which can be loaded with the compiler option F (inclusion of Pascal source text). Before entering this command make sure that your tape recorder is switched on and is in RECORD mode.

To write out a section of a program use:

```
W50,120,PLOT           ;write out the PLOT procedure.
```

To 'include' the section in another program:

```
100 END;
110
120 (*$F PLOT      'include' the PLOT procedure here.*)
130
140 PROCEDURE MORE;    (*the rest of program.*)
150
```

4.2.5 Compiling and Running from the Editor.

Command: C n

This causes the text starting at line number n to be compiled. If you do not specify a line number then the text will be compiled from the first existing line. For further details see Section 0.2.

Command: R

The previously compiled object code will be executed, but only if the source has not been expanded in the meantime - see Section 0.2 for more detail.

Command: T n

This is the 'T'ranslate command. The current source is compiled from line n (or from the start if n is omitted) and, if the compilation is successful, you will be prompted with 'Ok?': if you answer 'Y' to this prompt then the object code produced by the compilation will be moved to the end of the runtimes (destroying the compiler) and then the runtimes and the object code will be dumped out to tape with a filename equal to that previously defined for the 'find' string. You may then, at a later stage, load this file into memory, using the HP4T loader, whereupon it will automatically execute the object program. Note that the object code is located at and moved to the end of the runtimes so that, after a 'T'ranslate you will need to reload the compiler - however this should present no problems since you are only likely to 'T'ranslate a program when it is fully working.

If you decide not to continue with the dump to tape then simply type any character other than 'Y' to the 'Ok?' prompt; control is returned to the editor which will still function perfectly since the object code was not moved.

4.2.6 Other Commands.

Command: B

This simply returns control to the operating system. For details of how to re-enter the compiler refer to the HP4T Alteration Guide and your Implementation Note.

Command: O n,m

Remember that text is held in memory in a tokenised form with leading spaces shortened into a one character count and all HP4T Reserved Words reduced to a one character token. However if you have somehow got some text in memory, perhaps from another editor, which is not tokenised then you can use the 'O' command to tokenise it for you. Text is read into a buffer in an expanded form and then put back into the file in a tokenised form - this may of course take a little time to perform. A line range must be specified, or the previously entered values will be assumed.

Command: X

The 'X' command displays, in hexadecimal, the current end address of the compiler.

Command: S,,d

This command allows you to change the delimiter which is taken as separating the arguments in the command line. On entry to the editor the comma ',' is taken as the delimiter; this may be changed by the use of the 'S' command to the first character of the specified string d. Remember that once you have defined a new delimiter it must be used (even within the 'S' command) until another one is specified.

Note that the separator may not be a space.

4.3 An Example of the use of the Editor.

Let us assume that you have typed in the following program (using I10,10):

```
10 PROGRAM BUBBLESORT
20 CONST
30 Size = 2000;
40 VAR
50 Numbers : ARRAY [1..Size] OF INTEGER;
60 I, Temp : INTEGER;
70 BEGIN
80 FOR I:=1 TO Size DO Number[I] := RANDOM;
90 REPEAT
100 FOR I:=1 TO Size DO
110 Noswaps := TRUE;
120 IF Number[I] > Number[I+1] THEN
130 BEGIN
140 Temp := Number[I];
150 Number[I] := Number[I+1];
160 Number[I+1] := Temp;
170 Noswaps := FALSE
180 END
190 UNTIL Noswaps
200 END.
```

This program has a number of errors which are as follows:

Line 10 Missing semi-colon.

Line 30 Not really an error but say we want a size of 100.

Line 100 Size should be Size-1.

Line 110 This should be at line 95 instead.

Line 190 Noswapss should be Noswaps.

Also the variable Numbers has been declared but all references are to Number. Finally the BOOLEAN variable Noswaps has not been declared.

To put all this right we can proceed as follows:

F60,200,Number,Numbers and then use sub-command 'S' repeatedly.

E10 then the sequence X ; ENTER ENTER

E30 then _____ K C 1 ENTER ENTER

F100,100,Size,Size-1 followed by the sub-command 'S'.

M110,95

110 followed by ENTER.

E190 then X DELETE ENTER ENTER

65 Noswaps : BOOLEAN; .

N10,10 to renumber in steps of 10.

You are strongly recommended to work through the above example actually using the editor - you may find it a little cumbersome at first if you have been used to screen editors but it should not take long to adapt.

A.1.1 Error numbers generated by the compiler.

1. Number too large.
2. Semi-colon expected.
3. Undeclared identifier.
4. Identifier expected.
5. Use '=' not ':=' in a constant declaration.
6. '=' expected.
7. This identifier cannot begin a statement.
8. ':=' expected.
9. ')' expected.
10. Wrong type.
11. '.' expected.
12. Factor expected.
13. Constant expected.
14. This identifier is not a constant.
15. 'THEN' expected.
16. 'DO' expected.
17. 'TO' or 'DOWNTO' expected.
18. '(' expected.
19. Cannot write this type of expression.
20. 'OF' expected.
21. ',' expected.
22. ':' expected.
23. 'PROGRAM' expected.
24. Variable expected since parameter is a variable parameter.
25. 'BEGIN' expected.
26. Variable expected in call to READ.
27. Cannot compare expression of this type.
28. Should be either type INTEGER or REAL.
29. Cannot read this type of variable.
30. This identifier is not a type.
31. Exponent expected in real number.
32. Scalar expression (not numeric) expected.
33. Null strings not allowed (use CHR(0)).
34. '(' expected.
35. '*' expected.
36. Array index type must be scalar.
37. '..' expected.
38. ']' or ',' expected in ARRAY declaration.
39. Lowerbound greater than upperbound.
40. Set too large (more than 256 possible elements).
41. Function result must be type identifier.
42. ',' or ']' expected in set.
43. '..' or ',' or ']' expected in set.
44. Type of parameter must be a type identifier.
45. Null set cannot be the first factor in a non-assignment statement.
46. Scalar (including real) expected.
47. Scalar (not including real) expected.
48. Sets incompatible.
49. '<' and '>' cannot be used to compare sets.
50. 'FORWARD', 'LABEL', 'CONST', 'VAR', 'TYPE' or 'BEGIN' expected.
51. Hexadecimal digit expected.
52. Cannot POKE sets.
53. Array too large (>64K).
54. 'END' or ';' expected in RECORD definition.
55. Field identifier expected.
56. Variable expected after 'WITH'.
57. Variable in WITH must be of RECORD type.
58. Field identifier has not had associated WITH statement.
59. Unsigned integer expected after 'LABEL'.

60. " " " " 'GOTO'.
61. This label is at the wrong level.
62. Undeclared label.
63. The parameter of SIZE should be a variable.
64. Can only use equality tests for pointers.
- 65.
- 66.
67. The only write parameter for integers with two ':'-s is e:m:H.
68. Strings may not contain end-of-line characters.
69. The parameter of NEW, MARK or RELEASE should be a variable of pointer type.
70. The parameter of ADDR should be a variable.

A.1.2 Runtime error messages.

When a runtime error is detected then one of the following messages will be displayed, followed by ' at PC=XXXX', where XXXX is the memory location at which the error occurred. Often the source of the error will be obvious; if not, consult the compilation listing to see where in the program the error occurred, using XXXX to cross reference. Occasionally this does not give the correct result.

1. Halt
 2. Overflow
 3. Out of RAM
 4. / by zero also generated by DIV.
 5. Index too low
 6. Index too high
 7. Maths Call Error
 8. Number too large
 9. Number expected
 10. Line too long
 11. Exponent expected
- Runtime errors result in the program execution being halted.

A.2.1 Reserved Words.

AND	ARRAY	BEGIN	CASE	CONST	DIV	DO	DOWNT
ELSE	END	FOR	FORWARD	FUNCTION		GOTO	IF
IN	LABEL	MOD	NIL	NOT	OF	OR	
PACKED	PROCEDURE		PROGRAM	RECORD	REPEAT	SET	THEN
TO	TYPE	UNTIL	VAR	WHILE	WITH		

A.2.2 Special Symbols.

The following symbols are used by Hisoft Pascal 4 and have a reserved meaning:

+	-	*	/		
=	<>	<	<=	>=	>
()	[]		
{	}	(*	*)		
^	:=	.	,	;	:
'	..				

A.2.3 Predefined Identifiers.

The following entities may be thought of as declared in a block surrounding the whole program and they are therefore available throughout the program unless re-defined by the programmer within an inner block.

For further information see Section 2.

```

CONST    MAXINT = 32767;
TYPE    BOOLEAN = (FALSE,TRUE);
         CHAR (*The expanded ASCII character set*)
         INTEGER = -MAXINT..MAXINT;
         REAL (*A subset of the real numbers. See Section 1.3.*)
PROCEDURE WRITE; WRITELN; READ; READLN; PAGE; HALT; USER;
         POKE; INLINE; OUT; NEW; MARK; RELEASE; TIN; TOUT;
FUNCTION ABS; SQR; ODD; RANDOM; ORD; SUCC; PRED; INCH; EOLN;
         PEEK; CHR; SQRT; ENTIER; ROUND; TRUNC; FRAC; SIN;
         COS; TAN; ARCTAN; EXP; LN; ADDR; SIZE; INP;
    
```

A.3.1 Data Representation.

The following discussion details how data is represented internally by Hisoft Pascal 4.

A.3.1.1 Integers.

Integers occupy 2 bytes of storage each, in 2's complement form. Examples:

1 = #0001
256 = #0100
-256 = #FF00

The standard Z80 register used by the compiler to hold integers is HL.

A.3.1.2 Characters. Booleans and other Scalars.

These occupy 1 byte of storage each, in pure, unsigned binary. Characters: 8 bit, extended ASCII is used.

'E' = #45
'[' = #5B

Booleans

ORD(TRUE)=1 so TRUE is represented by 1.
ORD(FALSE)=0 so FALSE is represented by 0.

The standard Z80 register used by the compiler for the above is A.

A.3.1.3 Reals.

The (mantissa,exponent) form is used similar to that used in standard scientific notation - only using binary instead of denary. Examples

$$2 = 2 * 10^0 \quad \text{or} \quad 1.0_2 * 2^1$$

$$1 = 1 * 10^0 \quad \text{or} \quad 1.0_2 * 2^0$$

$$\begin{aligned} -12.5 &= -1.25 * 10^1 \quad \text{or} \quad -25 * 2^{-1} \\ &= -11001_2 * 2^{-1} \\ &= -1.1001_2 * 2^3 \quad \text{when normalized.} \end{aligned}$$

$$0.1 = 1.0 * 10^{-1} \quad \text{or} \quad \frac{1}{10} = \frac{1}{1010_2} = \frac{0.1}{101_2}$$

so now we need to do some binary long division..

```


0.0001100
-----
101 I 0.1000000000000000
      101
      ---
       110
       101
       ---
        1000
        101   at this point we see
        ---   that the fraction recurs

0.1
  2
= ---- = 0.0001100
  101  2

1.1001100 * 2^{-4}   answer.

```

So how do we use the above results to represent these numbers in the computer? Well, firstly we reserve 4 bytes of storage for each real in the following format:



sign: the sign of the mantissa; 1=negative, 0=positive.

normalized mantissa: the mantissa normalized to the form 1.XXXXXX with the top bit (bit 22) always 1 except when representing zero (HL=DE=0).

exponent: the exponent in binary 2's complement form.

Thus:

```

2 = 0 1000000 00000000 00000000 00000001 (#40,#00,#00,#01)
1 = 0 1000000 00000000 00000000 00000000 (#40,#00,#00,#00)
-12.5 = 1 1100100 00000000 00000000 00000011 (#E4,#00,#00,#03)
0.1 = 0 1100110 01100110 01100110 11111100 (#66,#66,#66,#FC)

```

So, remembering that HL and DE are used to hold real numbers, then we would have to load the registers in the following way to represent each of the above numbers:

```

2 = LD HL,#4000
   LD DE,#0100
1 = LD HL,#4000
   LD DE,#0000
-12.5 = LD HL,#E400
        LD DE,#0300
0.1 = LD HL,#6666
      LD DE,#FC66

```

The last example shows why calculations involving binary fractions can be inaccurate; 0.1 cannot be accurately represented as a binary fraction, to a finite number of decimal places.

N.B. reals are stored in memory in order ED LH

A.3.1.4 Records and Arrays.

Records use the same amount of storage as the total of their components.

Arrays: if n=number of elements in the array and s=size of each element then

the number of bytes occupied by the array is n*s.

e.g. an ARRAY[1..10] OF INTEGER requires 10*2 = 20 bytes
 an ARRAY[2..12,1..10] OF CHAR has 11*10=110 elements
 and so requires 110 bytes.

A.3.1.5 Sets.

Sets are stored as bit strings and so if the base type has n elements then the number of bytes used is: (n-1) DIV 8 + 1.

Examples:

a SET OF CHAR requires (256-1) DIV 8 + 1 = 32 bytes.
 a SET OF (blue,green,yellow) requires (3-1) DIV 8 + 1 = 1 byte.

A.3.1.6 Pointers.

Pointers occupy 2 bytes which contain the address (in Intel format i.e. low byte first) of the variable to which they point.

A.3.2 Variable Storage at Runtime.

There are 3 cases where the user needs information on how variables are stored at runtime:

- a. Global variables - declared in the main program block.
- b. Local variables - declared in an inner block.
- c. Parameters and returned values. - passed to and from procedures and functions.

These individual cases are discussed below and an example of how to use this information may be found in Appendix 4.

Global variables

Global variables are allocated from the top of the runtime stack downwards e.g. if the runtime stack is at #B000 and the main program variables are:

```
VAR      i:INTEGER;
          ch:CHAR;
          x:REAL;
```

then:

i (which occupies 2 bytes - see the previous section) will be stored at locations #B000-2 and #B000-1 i.e. at #AFFE and #AFFD.

ch (1 byte) will be stored at location #AFFE-1, i.e. at #AFFD.

x (4 bytes) will be placed at #AFF9, #AFFA, #AFFB and AFFC.

Local variables

Local variables cannot be accessed via the stack very easily so, instead, the IX register is set up at the beginning of each inner block so that (IX-4) points to the start of the block's local variables e.g.

```
PROCEDURE test;
```

```
VAR      i,j:INTEGER;
```

then:

i (integer - so 2 bytes) will be placed at IX-4-2 and IX-4-1 i.e. IX-6 and IX-5.

j will be placed at IX-8 and IX-7.

Parameters and returned values

Values parameters are treated like local variables and, like these variables, the earlier parameter is declared the higher address it has in memory. However, unlike variables, the lowest (not the highest) address is fixed and this is fixed at (IX+2) e.g.

```
PROCEDURE test(i:REAL; j:INTEGER);
```

then:

j (allocated first) is at IX+2 and IX+3.

i is at IX+4, IX+5, IX+6, and IX+7.

Variable parameters are treated just like value parameters except that they are always allocated 2 bytes and these 2 bytes contain the address of the variable e.g.

```
PROCEDURE test(i:INTEGER; VAR x:REAL);
```

then:

the reference to x is placed at IX+2 and IX+3; these locations contain the address where x is stored. The value of i is at IX+4 and IX+5.

Returned values of functions are placed above the first parameter in memory e.g.

```
FUNCTION test(i:INTEGER) : REAL;
```

then i is at IX+2 and IX+3 and space is reserved for the returned value at IX+4, IX+5, IX+6 and IX+7.

Appendix 4

ZX SPECTRUM SOUND

The following two procedures (defined in the order given bellow) are required to produce sound with HP4T.

(*This procedure uses machine code to pick up its parameters and then passes them to the BEEP routine within the SPECTRUM ROM.*)

```
PROCEDURE BEEPER (A, B : INTEGER);
BEGIN
  INLINE(#DD, #6E, 2, #DD, #66, 3, (*LD L,(IX+2) : LD H,(IX+3)*)
        #DD, #5E, 4, #DD, #56, 5, (*LD E,(IX+4) : LD D,(IX+5)*)
        #CD, #B5, 3, #F3)      (*CALL #3B5 : DI *)
END;
```

(*This procedure traps a frequency of zero which it converts into a period of silence. For non-zero frequencies the frequency and length of the note are approximately converted to the values required by the SPECTRUM ROM routine and this is then called via BEEPER.*)

```
PROCEDURE BEEP (Freq : INTEGER; Length : REAL);
VAR I : INTEGER;
BEGIN
  IF Freq=0 THEN FOR I:=1 TO ENTIER(12000*Length) DO
  ELSE BEEPER(ENTIER(Freq*Length),ENTIER(437500/Freq-30.125))
  FOR I:= 1 TO 100 DO      (*short delay between notes*)
  END;
```

Example of the use of BEEP:

```
BEEP ( 262, 0.5 );      (*sounds middle C for 0.5 seconds*)
BEEP ( 0, 1 );         (*followed by a one second silence.*)
```

SOME EXAMPLE HP4T PROGRAMS.

(*Program to illustrate the use of TIN and TOUT. The program constructs a very simple telephone directory on tape and then reads it back. You should write any searching required.*)

PROGRAM TAPE;

CONST

Size = 10; (*Note that 'Size' is in upper
and lower case - not 'SIZE'.*)

TYPE

Entry = RECORD
Name : ARRAY [1..10] OF CHAR;
Number : ARRAY [1..10] OF CHAR
END;

VAR

Directory : ARRAY [1..Size] OF Entry;

I : INTEGER;

BEGIN (*Set up the directory..*)

FOR I:= 1 TO Size DO

BEGIN

WITH Directory[I] DO

BEGIN

WRITE('Name please');

READLN;

READ(Name);

WRITELN;

WRITE('Number please');

READLN;

READ(Number);

WRITELN

END

END;

(*To dump the directory to tape use..*)

TOUT('Director',ADDR(Directory),SIZE(Directory))

(*Now to read the array back to the following..*)

TIN('Director',ADDR(Directory))

(*And now you can process the directory as you wish.....*)

END.


```

10 (*Program to list lines of a file in reverse order.
20 Shows use of pointers, records, MARK and RELEASE.*)
30
40 PROGRAM ReverseLine;
50
60 TYPE elem=RECORD          (*Create linked-list structure*)
70     next: ^elem;
80     ch: CHAR
90     END;
100 link:=^elem;
110
120 VAR prev,cur,heap: link;  (*all pointers to 'elem'*)
130
140 BEGIN
150     REPEAT                (*do this many times*)
160         MARK(heap);      (*assign top of heap to 'heap'*)
170         prev:=NIL;       (*points to no variable yet.*)
180         WHILE NOT EOLN DO
190             BEGIN
200                 NEW(cur); (*create a new dynamic record*)
210                 READ(cur^.ch); (*and assign its field to one
220                     character from file.*)
230                 cur^.next:=prev; (*this field's pointer addresses*)
240                 prev:=cur      (*previous record.*)
250             END;
260
270 (*Write out the line backwards by scanning the records
280 set up backwards.*)
290
300     cur:=prev;
310     WHILE cur <> NIL DO  (*NIL is first*)
320         BEGIN
330             WRITE(cur^.ch); (*WRITE this field i.e. character*)
340             cur:=cur^.next  (*Adress previous field.*)
350         END;
360     WRITELN;
370     RELEASE(heap);      (*Release dynamic variable space.*)
380     READLN              (*Wait for another line*)
390     UNTIL FALSE        (*Use EDIT to exit*)
400 END.

```

```

10  (*Program to show the use of recursion*)
20
30  PROGRAM FACTOR;
40
50  (*This program calculates the factorial of a number input
60  from the keyboard 1) using recursion and 2) using an
70  iterative method.*)
80  TYPE
90    POSINT = 0..MAXINT;
100
110  VAR
120    METHOD : CHAR;
130    NUMBER : POSINT;
140
150  (*Recursive algorithm.*)
160
170  FUNCTION RFAC(N : POSINT) : INTEGER;
180
190    VAR F : POSINT;
200
210  BEGIN
220    IF N>1 THEN F:= N * RFAC(N-1)    (*RFAC invoked N times*)
230      ELSE F:= 1;
240    RFAC := F
250  END;
260
270  (*Iterative solution*)
280
290  FUNCTION IFAC(N : POSINT) : INTEGER;
300
310    VAR I,F: POSINT;
320  BEGIN
330    F := 1;
340    FOR I := 2 TO N DO F := F*I;    (*Simple Loop*)
350    IFAC := F
360  END;
370
380  BEGIN
390    REPEAT
400      WRITE('Give method (I or R) and number ');
410      READLN;
420      READ(METHOD,NUMBER);
430      IF METHOD = 'R'
440        THEN WRITELN(NUMBER,'! = ',RFAC(NUMBER))
450        ELSE WRITELN(NUMBER,'! = ',IFAC(NUMBER))
460    UNTIL NUMBER=0
470  END.

```

```

10 (*Program to show how to 'get your hands dirty'!
20 i.e. how to modify Pascal variables using machine code.
30 Demonstrates PEEK, POKE, ADDR and INLINE.*)
40
50 PROGRAM divmult2;
60
70 VAR r:REAL;
80
90 FUNCTION divby2(x:REAL):REAL;      (*Function to divide
100                                by 2.... quickly*)
110 VAR i:INTEGER;
120 BEGIN
130   i:= ADDR(x)+1;                  (*Point to the exponent of x*)
140   POKE(i,PRED(PEEK(i,CHAR)));    (*Decrement the exponent of x.
150                                see Appendix 3.1.3.*)
160   divby2:=x
170 END;
180
190 FUNCTION multby2(x:REAL):REAL;    (*Function to multiply by
200                                by 2.... quickly*)
210 BEGIN
220   INLINE(#DD,#34,3);              (*INC (IX+3) - the exponent
230                                of x - see Appendix 3.2.*)
240   multby2:=x
250 END;
260
270 BEGIN
280   REPEAT
290     WRITE('Enter the number r ');
300     READ(r);                      (*No need for READLN - see
310                                Section 2.3.1.4*)
320
330     WRITELN('r divided by two is',divby2(r):7:2);
340     WRITELN('r multiplied by two is',multby2(r):7:2)
350   UNTIL r=0
360 END.

```